



Release Notes

TRIMBLE® LIVECOUNT™ SOFTWARE VERSION 5.2

Trimble is pleased to offer **Release 5.2** of the **Trimble® LiveCount™** software. This document provides enhancement/modification, installation, and compatibility information pertaining to this release.

This document provides the following information:

- *Modifications*
- *Compatibility*
- *Upgrade Installation Notes*

Modifications

Features

- The pdf library has been updated to make processing drawings faster and more stable.
- When changing the scale of a drawing after takeoff has been done, all takeoff affected should have their lengths updated in the Estimating solution.

Other Modifications

- Under some circumstances it was possible for the program to not allow the renaming of tree branches. This has been corrected.
- When moving traces in the tree, it was possible that the trace wouldn't be removed from the old branch. This now works as expected.
- When performing a pattern search, it was possible under some circumstances for the application to hang requiring a restart of the application. This has since been corrected.
- When deleting a measurement from within Accubid™ Classic Estimating, it was possible for the measurement to continue to display in the LiveCount Measurement List window. This now functions as expected.
- When switching projects, sometimes LiveCount would switch back to the previous project, rather than continuing in the same project as expected. This has been corrected.

9131 Keele St., Suite A7, Vaughan, Ontario, L4K0G7
1-800-361-3030 & accubidsupport@trimble.com

mep.trimble.com


TRANSFORMING THE WAY THE WORLD WORKS



Compatibility

This release of the Trimble Accubid LiveCount™ software is compatible with the following applications:

- **Trimble® Accubid™ Enterprise, Version 5.0.3 or newer**
- **Trimble® Accubid™ Classic, Version 13.0** (*it is not compatible with earlier versions of the Classic software*)

 **Tip** – If you experience any version compatibility issues, please contact Trimble MEP Client Services at 1-800-361-3030 for assistance.


- **Trimble® LiveCount™ Server**

The LiveCount Server is a utility installed and run on your network server. This allows you to have a central location for LiveCount database files, which will greatly increase performance.

If you have five or more estimators using the LiveCount database concurrently, Trimble recommends moving to the LiveCount Server. This will substantially increase software performance, allowing for faster completion of LiveCount processes.

Note: The LiveCount Server is a separate product, requiring a separate license. The cost of the LiveCount Server license is not included in the base price of LiveCount. Please contact your Trimble sales representative for more information.

Upgrade Installation Notes

 **Tip** – You must follow the instructions outlined below to ensure proper behavior of your software after installation and configuration is complete.

Backup Data Files

Trimble recommends you backup up your LiveCount data files before upgrading to the LiveCount Version 5.2 software.

- LiveCount4.0Projects.ctr
- LiveCount4.0Standards.ctr
- ElectricalSymbols.bmp (if using custom point symbols)
- ElectricalSymbols.txt (if using custom point symbols)

LiveCount Versions 3.0 or above

If you have LiveCount version 3.0 or above installed, you can simply install the version 5.1 release over your existing software. Note: Uninstalling is not required.

LiveCount Versions 2.5 / 2.5.1

You need to uninstall your existing LiveCount software before you install the LiveCount software, version 3.0 update.

LiveCount Server

If you choose to move to the LiveCount Server application, a detailed installation document is available. This document outlines the steps required to properly install the server application, as well as connecting workstations to the network database.